

HP Availability Manager - Version 3.0-2

Release Notes

February 2009

IMPORTANT

In these Release Notes, the term **Combined kit** refers to the Data Analyzer/Data Server kit.

The Release Notes documents additions and changes for version 3.0-2 of the Combined kit and version 3.0-2A of the Data Collector kit.

Be sure to read the following sections:

- Section 1.1—contains information about WAN support and security measures for communication between the Data Analyzer and Data Server.
 - Section 1.3 and Section 1.4. Note Section 1.3 describes the requirement that the installation disk be an ODS-5 formatted disk on OpenVMS systems using the Combined kit. Note Section 1.4 describes how to install the Combined kit on any ODS-5 formatted disk.
 - Section 1.2—explains that the AVAIL_MAN_ANA kit has been renamed to AVAIL_MAN_ANA_SRVR.
-

The following notes address late-breaking information and known problems for the HP Availability Manager Version 3.0-2. These notes are in the following categories:

- New and changed features
- Installation notes
- Problems corrected
- Operation notes
- Display notes

1 New and Changed Features

The following section discusses new and changed features introduced in Version 3.0-2 of the Availability Manager.

1.1 Data Collection Over a Wide-Area Network (WAN)

The Availability Manager can now collect data over a WAN. This possible because a new software component has been added to the Availability Manager software: the Data Server.

The Data Server resides on the same local-area network (LAN) as the OpenVMS systems that you want to monitor. The Data Analyzer connects to the Data Server over the WAN. Using the IP protocol suite, data packets are transmitted between the Data Analyzer and the Data Server. This method of transmitting data packets allows the Data Analyzer to reside anywhere on the WAN.

Data Server setup and usage details are in the *HP OpenVMS Availability Manager User's Guide*, Sections 1.1 and 1.2, as well as Sections 2.2 through 2.6.

The Availability Manager uses Transport Layer Security (TLS) for secure WAN communication between the Data Analyzer and Data Server. See the Chapter 2 of *HP OpenVMS Availability Manager User's Guide* for steps that you must perform in order to set up this security mechanism.

1.2 Data Analyzer Kit Renamed to AVAIL_MAN_ANA_SRVR

The AVAIL_MAN_ANA kit has been renamed to AVAIL_MAN_ANA_SRVR because the new kit contains both the Data Analyzer and Data Server.

Note

You need to uninstall the AVAIL_MAN_ANA kit before installing the new AVAIL_MAN_ANA_SRVR kit.

1.3 Use of Java Version 5.0 for the Combined Kit

The Availability Manager Combined kit uses the 5.0 version of the Java Virtual Machine. (Java Version 5.0 is also known as 1.5.)

The following changes are the result of this Java upgrade:

- For OpenVMS systems using the Data Analyzer or Data Server, the installation disk must be an ODS-5 disk.
- Performance on OpenVMS has improved.

1.4 Ability to Install the Combined Kit on a Non-system Disk

In Version 3.0-2, you can install the Combined kit, AVAIL_MAN_ANA_SRVR, on a non-system ODS-5 formatted disk. This kit removes the requirement that the kit be installed on the system disk.

To install on a non-system ODS-5 formatted disk, use the /DESTINATION qualifier of the \$ PRODUCT INSTALL command to specify the installation disk and directory; for example:

```
$ PRODUCT INSTALL AVAIL_MAN_ANA_SRVR /DESTINATION=DISK$SYS_V83:[SOFTWARE]
```

The manual *HP Availability Manager Installation Instructions* details how to do the installation.

1.5 New Data Columns in System Overview and Related Event Additions and Changes

Version 3.0-2 introduces three new data columns in the System Overview Window.

Table 1 New Data Columns

Data Column	Description
PFLT5	Total page fault rate and hard fault rate
PFW/COM	Number of processes in PFW and COM states
DC	Data Collector capability version and Managed Object registration status

Version 3.0-2 also changed the CPU Qs column. The states summed in this column are now COLPG, COMO, FPG, and MWAIT. The column also displays the individual state counts if the total is greater than zero. The COM and PFW state counts that used to be included in the CPU Qs count have been moved to the new PFW/COM column.

New events in Version 3.0-2 follow. The last three result from the new PFW/COM column and changes to the CPU Qs column.

Table 2 New Events

Data Column	Description
HALNR	High alignment fault rate
HICMOQ	Many processes waiting in COMO
HIPFWQ	Many processes waiting in PFW state
PRCCMO	Process waiting in COMO

These events have changed as a result of the column changes.

Table 3 Changed Events

Event	Description
HICOMQ	Many processes waiting in COM
HIPWTQ	Many processes waiting in COLPG or FPG
PRCCOM	Process waiting in COM

1.6 Data Collection for Logical Disk (LDcn:) devices

The Data Analyzer now collects data on Logical Disks. These devices show up in the Disk Status and Disk Volume displays.

1.7 System Memory and Alignment Faults in Mem Column Tooltip

The Mem column in the System Overview Window now shows the total amount of memory on the system, and the number of page faults by mode.

1.8 Event Log Enhancements

With the advent of WAN support, there is an Event Log for each connection that the Data Analyzer is using, instead of one Event Log for the Data Analyzer session.

The Event Log now contains an entry when a threshold event has been cancelled. This new entry allows you to determine how long a threshold has been exceeded.

Along with the new entry for cancelled threshold events, three new columns have been added to the Event Log. These columns are as follows:

Table 4 New Event Columns

Event Column	Description												
Status	The value describes the status of the event. Values are as follows: <table><tr><th>Status Value</th><th>Description</th></tr><tr><td>INFO</td><td>This event is informational.</td></tr><tr><td>BEGIN</td><td>The event entry marks the beginning of the interval when the values for an event have exceeded the threshold.</td></tr><tr><td>END</td><td>The event entry marks the end of the interval when the values for an event have exceeded the threshold.</td></tr><tr><td>CANCELLED</td><td>The event entry marks when the event was removed because the data used to evaluate the event is now longer being collected.</td></tr><tr><td>EXPIRED</td><td>The event entry marks when the event has expired.</td></tr></table>	Status Value	Description	INFO	This event is informational.	BEGIN	The event entry marks the beginning of the interval when the values for an event have exceeded the threshold.	END	The event entry marks the end of the interval when the values for an event have exceeded the threshold.	CANCELLED	The event entry marks when the event was removed because the data used to evaluate the event is now longer being collected.	EXPIRED	The event entry marks when the event has expired.
Status Value	Description												
INFO	This event is informational.												
BEGIN	The event entry marks the beginning of the interval when the values for an event have exceeded the threshold.												
END	The event entry marks the end of the interval when the values for an event have exceeded the threshold.												
CANCELLED	The event entry marks when the event was removed because the data used to evaluate the event is now longer being collected.												
EXPIRED	The event entry marks when the event has expired.												
EventKey	A hex value identifying an event for a node. For instance, all HINTER events for a node have the same value. Each time the HINTER event is signaled for a node, the value will be the same, making it easy to search for all the HINTER events for a node.												
EventID	A hex value identifying an individual event. For instance, if the HICOMQ event on node SAM is signaled, the BEGIN and END/CANCELLED/EXPIRED entries that mark when the event was signaled and cancelled will have the same value. The next time the HICOMQ event is signaled on node SAM, the hex value will be different. This value makes it easy to find the entry that signals when the event has been cancelled.												

1.9 New STATUS Command Option in SYS\$STARTUP:AMDS\$STARTUP Command Procedure

The STATUS command option shows the current state of the Data Collector; for example, RMDRIVER STOPPED and RMDRIVER STARTED.

To display help on the output of this new option, enter the following command:

```
$ SYS$STARTUP:AMDS$STARTUP HELP STATUS
```

Examples of a STATUS command and output messages are the following:

```
$ @SYS$STARTUP:AMDS$STARTUP STATUS
```

Current status of AM/DECams Data Collector device RMA0:

```
RMA0: is started and is ready to accept requests for data
      and can accept a connection from a Data Analyzer
RMA0: is set to log data requests generating security violations to
      OPCOM (AMDS$RM_OPCOM_READ is set to TRUE)
RMA0: is set to log fixes generating security violations to OPCOM
      (AMDS$RM_OPCOM_WRITE is set to TRUE)
RMA0: is using VCI for network communications
```

1.10 New LOG Command Option in SYS\$STARTUP:AMDS\$STARTUP Command for START and RESTART Procedure

The START and RESTART command options support the LOG option. This option displays the configuration data that is loaded into the Data Collector. This option is useful to confirm the actual data gathered and loaded.

An example of using the LOG option follows:

```
$ SYS$SYSTARTUP:AMDS$STARTUP START LOG
```

1.11 Windows Availability Manager Software Can Use an FDDI Network Adapter

You can now use an FDDI network adapter to communicate with the network on a Windows version of the Availability Manager Data Analyzer. (Note that the OpenVMS Availability Manager software can already use an FDDI network adapter.)

1.12 Lock Contention Filter Page Now Allows Entry in Hex

The Lock Contention Filter page has been enhanced to display any entry in hex and allows entering hex values for an entry. There are 16 hex fields for the first 16 bytes of a resource name. A blank field indicates that there is no value for that byte.

The ability to edit all 31 characters of a resource name will be done in a future release.

1.13 Fix to Force a Disk Volume out of Mount Verify State

A new fix has been added to take a disk volume that is in a mount verify state and force it into a mount verify timeout state. This fix is available by right-clicking on any disk entry in the Disk Status Summary or Disk Volume Summary of a node pane.

1.14 Fix to Force a Shadow Set Member out of a Shadow Set

A new fix has been added to take a shadow set member in a mount verify state out of a shadow set. This has the same effect as the DCL command \$ SET SHADOW/FORCE_REMOVAL ddcu: This fix is available by right-clicking on any shadow set member entry in the Disk Status Summary or Disk Volume Summary of a node pane. Note: To show shadow set members in these two summaries, you need to bring up the Disk Status filter and set the Transaction count to zero.

1.15 Data Analyzer Supports Change of MAC Address on Data Collector System

The Data Analyzer now supports a change of MAC address from an OpenVMS system. The MAC address of a system may change if certain network protocol stacks are started or modified, and is usually seen if the \$@SYSS\$STARTUP:AMDS\$STARTUP START command is executed early in the system boot sequence. If this occurred in previous releases of the Availability Manager, the usual behavior is to display the system twice in the System Overview window - one entry is color-coded black, and the other is yellow, and no data is collected for the system.

The following events are affected by this change.

Table 5 Events Affected by MAC Address Feature

Event	Description
CFGDON	Current MAC address from system is added to the event text
PTHLST	Last known MAC address from system is added to the event text
CHGMAC	New event showing the current MAC address the system is using
NEWMAC	New event showing that a new MAC address is recorded for the system

1.16 Changed Disk Status Filter Mount Count to Display Shadow Set Members

The default mount count in the Disk Status filter has been set from one to zero. This setting allows shadow set members to be displayed in the Disk Status Summary display. This was done in conjunction with the shadow set member fix in Section 1.14.

1.17 Changed I/O Filter Open File Count Default

The default open file count in the I/O filter has been set from three to one. The default setting of three open files is from the DECams application, but often filters out processes doing I/O simply because only one or two files are open for the process.

1.18 Starting the Data Analyzer or Data Server on OpenVMS Checks for Necessary Logicals

A check for all the necessary logical names has been added to the startup of the Data Analyzer or Data Server. This ensures that the Data Analyzer and Data Server can access various files needed for a correct startup. If an error message appears saying that all the logical names aren't defined, make sure to compare your SYSS\$MANAGER:AMDS\$LOGICALS.COM file with the file SYSS\$MANAGER:AMDS\$LOGICALS.TEMPLATE.

1.19 Data Analyzer Logs Now Incorporate Data and Time in File Name

Data Analyzer and Data Server log files now incorporate the date and time in the file name. This helps to show when the file was created, and on Windows systems where the file system doesn't save versions of a file, the older log files are not deleted when newer versions are created. File names are now in the form *_YYYYMMDD-HHMM.*.

1.20 Default Hello Multicast Interval Changes

The default and secondary intervals in AMDS\$LOGICALS.COM have been changed from 30 and 90 to 10 and 15 seconds respectively. The older defaults were appropriate for older, slower networks of a number of years ago. The change for more modern networks allows the Data Analyzer to discover OpenVMS systems more quickly. This change is made in the file SYSS\$MANAGER:AMDS\$LOGICALS.TEMPLATE. Carry this change into your SYSS\$MANAGER:AMDS\$LOGICALS.COM file to change the Data Collector behavior.

1.21 Option to Increase OpenVMS Data Analyzer Performance When Displayed on a Remote System

The logical AMDS\$AM_DISABLE_OFFSCREEN_PIXMAP_SUPPORT controls whether or not the Java Virtual Machine uses offscreen pixmap support. Disabling this support can increase performance, especially when the Data Analyzer display is on a remote system using TCP/IP. If the performance of the OpenVMS Data Analyzer in this situation is slow, you can try setting this logical to TRUE to see if this helps in your situation. This change is made in the file SYSS\$MANAGER:AMDS\$LOGICALS.TEMPLATE. Carry this change into your SYSS\$MANAGER:AMDS\$LOGICALS.COM file to enable use of the AMDS\$AM_DISABLE_OFFSCREEN_PIXMAP_SUPPORT logical.

2 Installation Notes

The notes in this section are related to the preinstallation and installation of the Availability Manager software.

2.1 Check Date of AMNDIS50.SYS on Windows Systems After Installing Version 3.0-2

After installing the Version 3.0-2 Windows kit, check the date of the AMNDIS50.SYS file. This file is on the Windows system disk, usually in C:\WINDOWS\system32\drivers. The date should be November 28, 2006. If the date is earlier than this, you need to uninstall the Availability Manager software, and then reinstall it. Make sure to reboot your system when you are prompted to do so. This usually fixes the problem. The problem is being investigated. It is important to have the latest AMNDIS50.SYS file as it has fixes in it to prevent some system crashes when two Data Analyzers are started at the same time.

2.2 Uninstall Data Analyzer Kits Before Installing the Combined Kit for Version 3.0-2

Before installing the Version 3.0-2 AVAIL_MAN_ANA_SRVR kit, you must uninstall the old AVAIL_MAN_ANA kit. You cannot install the new kit over the old one because of restrictions in the \$ PRODUCT INSTALL command.

(Note that the Data Analyzer kit, ANA_MAN_ANA in previous versions, has been renamed to AVAIL_MAN_ANA_SRVR in Version 3.0-2; this new name better reflects the Data Analyzer and Data Server combination.)

2.3 Uninstall Versions of the Availability Manager Prior to 2.4 Before Installing the Version 3.0-2 Kit

On both Windows and OpenVMS systems, check the following list to see if any item applies to you. If so, follow the instructions in the appropriate section before installing Version 3.0-2:

- On Windows systems, you must first uninstall Versions 2.3 and lower kits. On Versions 2.4 and higher, you can install new kits over prior kits.
- On OpenVMS systems, perform one of the following steps:
 - If you have never installed the Availability Manager on your system, you can install Version 3.0-2 directly.
 - If you have installed a version of the Availability Manager prior to Version 2.4 and you are running OpenVMS Version 6.2 through Version 7.3-1 or its variants, you must perform the following steps:
 - a. Uninstall the previous version of the Availability Manager.
 - b. Install the Availability Manager Data Collector Version 2.4 kit.
 - c. Install the Version 3.0-2 Combined kit.
 - If you have installed a version of the Availability Manager prior to Version 2.4 and you are running OpenVMS Version 7.3 or higher, you must perform the following steps:
 - a. Uninstall the previous version of the Availability Manager.
 - b. Install the Version 3.0-2 Combined kit.

These requirements are explained in the Version 3.0-2 installation instructions.

2.4 Installing from an ODS-5 Disk

If you install the Version 3.0-2 kit from an ODS-5 disk, the file name for the kit must be in all-capital letters for the kit to be installed correctly.

2.5 Copy Your AVAILMAN.INI File

Prior to installation, you might want to make a copy of your AVAILMAN.INI file to save your customizations such as event threshold settings and the groups you usually monitor. On Windows systems, also delete any desktop shortcuts for previous versions of the Availability Manager because they will be invalid once the new version is installed.

3 Problems Corrected

The following sections discuss problems corrected in Version 3.0-2 of the Availability Manager.

3.1 Alignment Faults in the Data Collector Have Been Fixed

The remaining alignment faults in the Data Collector (SYSSRMDRIVER.EXE) have been found and fixed.

3.2 Password Encryption Now Enabled by Default

The password encryption feature introduced in Version 2.5 was not enabled as expected. This meant that the password for the Data Collector was passed in plain text. This problem has now been corrected.

3.3 Problem Starting Data Analyzer When DCL Extended Parsing Is On

On OpenVMS systems, when the DCL parsing style was set to extended (\$ SET PROCESS/PARSE_STYLE=EXTENDED), starting the Data Analyzer resulted in an unrecognized option error:

```
Unrecognized option: -CP
Could not create the Java virtual machine.
```

This problem has been corrected.

3.4 Sizing of Displays Corrected

The updated Data Analyzer now sizes and displays tables and sections of a window correctly—according to the size of the font. The Lock Contention and Cluster displays are now more readable as well.

These changes are especially evident on OpenVMS systems.

3.5 Data Analyzer Performance Improvements

The reworking of the Data Analyzer to initiate and use connections to the Data Server also made processing of data more efficient. The result has been improved performance in the Data Analyzer.

3.6 Lock Contention Data Collection Performance Improvements

For systems with large resource hash tables, the data collection for lock contention have been improved, and result in less network traffic.

3.7 Starting the Version 2.6 Data Analyzer Would Fail on Some I64 Systems

Starting the Data Analyzer Version 2.6 would result in a Java VM stack dump on some I64 systems that use certain versions of the Montecito chip set. The output looks similar to the example below:

```
I64VMS> avail/avail
%SYSTEM-F-ACCVIO, access violation, reason mask=00,
  virtual address=000000000000 0454, PC=00000000002975D0, PS=0000001B
%TRACE-F-TRACEBACK, symbolic stack dump follows
image      module      routine      line      rel PC      abs PC
JAVA$HOTSPOT_SHR  IA64_SPECS  ia64_get_issue_port
                                     9950 0000000000000060 00000000002975D0
JAVA$HOTSPOT_SHR  IPACK      ipack_generate_nop_bits
                                     22580 00000000000000EA0 0000000000298C00
JAVA$HOTSPOT_SHR  TL_HS      ipack_init_nops
                                     22215 00000000000000C10 00000000002A2220
...
```

This problem was in earlier 1.4 versions of the Java Virtual Machine. This has been fixed since Version 3.0-2 of the Availability Manager uses a 1.5 version of the Java Virtual Machine.

3.8 System Uptime Value Wraparound Fixed

For systems up over 500 days, the system uptime wrap around and continue counting from a zero value. This has been fixed.

3.9 HIHRDP Event Changed to Use Hard Page Fault Rate

The documentation for the HIHRDP event states that the hard page fault rate is compared to the threshold. However, the read I/O rate was used instead. This has been fixed to use the hard page fault rate as advertised in the documentation.

3.10 Customization of Threshold Values Would Fail with “ERR” Status

On various occasions, trying to change a threshold value for an event would result in a red “ERR” status in the field. This has been fixed.

3.11 Single Process Pane Now Displays Process Type Correctly

In previous versions of the Data Analyzer, “(DETACHED)” process type was displayed for all processes, regardless of type. This has been fixed.

4 Operation Notes/Restrictions

The following sections contain notes pertaining to the operation of the Availability Manager Version 3.0-2. The sections are subdivided into field test versions and a final section that contains notes applying to all field test versions.

4.1 Notes for Version 3.0-2

The following sections contain notes that apply the Availability Manager Version 3.0-2.

4.1.1 Changing the Number of the Port the Data Server Uses

The default port number for the Data Server is 9819. If you want to use a different port number, do one of the following:

- For Windows systems, modify the Data Server startup shortcut. Right-click the shortcut, and choose Properties. In the “Target:” field, find the number 9819. Change this number to the port you want.
- For OpenVMS systems, use the /PORT_NUMBER qualifier to specify a different port number; for example:

```
$ AVAIL/SERVER/PORT_NUMBER=5498
```

4.1.2 Changing the Network Adapter the Data Server Uses on Windows Systems

On Windows systems, the Data Server picks up the first available network adapter for data communications. If it selects an undesirable network adapter—for example, a wireless adapter on a laptop—you can disable this selection by unchecking “HP Availability Manager NDIS 5.0 Protocol Driver” in the Network Properties for the network adapter.

4.1.3 Stopping the Data Server

You can stop the Data Server in one of the following ways:

- On Windows systems, close the Windows console window where the Data Server is running.
- On OpenVMS systems, Ctrl/Y stops the Data Server in interactive processes. Stopping the process stops the Data Server for batch processes.

4.1.4 Data Server Uses Only First Network Adapter

This version of the Data Server on Windows selects the first network adapter that it discovers when it starts up. The network adapter it chooses is displayed in a log message on the screen.

Plans for a future release include the ability to select the network adapter of your choice.

4.1.5 Starting the Data Server Might Trigger Windows Security Alert

On Windows systems, a security alert from the Windows firewall or third-party firewall might be displayed for the Java 2 Platform Standard Edition binary. The Data Server needs to accept connections as part of its normal operation. Tell the firewall to “Unblock” the program.

4.2 Notes for All Versions

The following sections contain notes that apply to all versions of the Availability Manager.

4.2.1 Running Reflective Memory by GE Fanuc and Availability Manager

The Reflective Memory product by GE Fanuc sets up the device RMA0: as part of its normal operation. Because the Availability Manager Data Collector also creates the device RMA0:, both products cannot run on the same node at the same time.

4.2.2 Administrator Account Required to Run the Availability Manager

On Windows 2000 and Windows XP platforms, you must run the Data Analyzer or Data Server from an account in the Administrator group. This restriction will be removed in a future release of the Availability Manager.

4.2.3 Problem Displaying Large Numbers of Processes or Disks

Very busy networks can sometimes interfere with the transfer of data between the Data Analyzer and the Data Collector. This problem is noticeable when you display large numbers of disks or processes. The number of disks or processes might change temporarily because of a lost data message. This problem will be corrected in a future release.

4.2.4 Local Administrator Account Required for Windows Installation

To install the Availability Manager on a Windows system, you must use the local Administrator account. Some users have had problems when they use a Windows domain account that has Administrator privileges instead. For example, a failure message might appear saying "Failure to install AMNDIS50" after most of the installation is complete. This problem will be corrected in a future release.

5 Display Notes

The following sections contain notes pertaining to the display of Data Analyzer data on all platforms and on OpenVMS systems.

5.1 Problems Using the Data Analyzer on All Platforms

The following sections contains subsections pertaining to the display of the Data Analyzer on Windows and on OpenVMS platforms in Version 3.0-2.

5.1.1 Events Sometimes Displayed After Background Collection Stops

The Data Analyzer sometimes displays events after users customize their systems to stop collecting a particular kind of data. This is most likely to occur when the Data Analyzer is monitoring many nodes. Under these conditions, a data handler sometimes clears events before all pending packets have been processed. The events based on the data in these packets are displayed even though users have requested that this data not be collected.

5.1.2 Truncated LAN Channel Summary Display

On versions of OpenVMS prior to Version 7.3-1, the LAN Channel Summary display might be disabled for some OpenVMS nodes if there are more than seven channels for that virtual circuit. This problem results from a restriction in the OpenVMS Version 7.3 PEDRIVER. For this condition, the following error message is displayed:

```
Error retrieving ChSumLAN data, error code=0x85 (Continuation data
disallowed for request)
```

This problem was corrected in the OpenVMS Version 7.3-1 PEDRIVER.

5.2 Problem Using the Data Analyzer on OpenVMS Systems: Long Runs Exhaust XLIB Resource ID

On older versions of DECwindows Motif, a resource ID allocation scheme works poorly with the Motif support in Java for OpenVMS. As a result, long-running Availability Manager sessions might stop updating the display at a time that depends on the speed of the OpenVMS machine. For example, a session running on a dual-processor 275 MHz system reported the following after 14 hours:

```
Xlib: resource ID allocation space exhausted!
```

On faster machines, this message was reported after only 8 hours. This problem appears to be corrected in DECwindows Motif Version 1.3-1.